KINTECHASIA

Kintech EA - Copy mode

Copy the orders of a master account

Kintech_EA · Version **1.40** · Updated 2026-11-09
Online version: https://kintech.asia/guide/copy

Contents

Overview

Requirements

1. Install the EA and allow the server

2. Attach the EA to a chart

3. Settings (SETTINGS tab)

4. How copying works

5. Read the COPY tab

6. Stop copying (DISABLE COPY)

7. Change the copy signal

8. How copied orders look

9. ERROR LOGS

Overview

Copy mode lets Kintech_EA copy the orders of a KintechAsia **master account** to your MT5 account. You choose a **copy signal** from the list KintechAsia publishes and choose the lot size. Every new order of the master is copied, and when the master closes a chain your copies close too.

> **NOTE**
> Your settings stay on your computer. To prepare copy reports, the EA sends your balance, equity and trade history to the KintechAsia server.

Requirements

- MetaTrader 5 (desktop, Windows) that stays online - a VPS is recommended.
- A **Hedging** account. Netting accounts are refused.
- An active Kintech license for the account number. Demo accounts get a trial automatically.
- The **Kintech_EA.ex5** file.

1. Install the EA and allow the server

1. In MT5 open **File > Open Data Folder > MQL5 > Experts** and copy **Kintech_EA.ex5** there. Then right-click **Expert Advisors** in the Navigator and choose **Refresh**.
2. Open **Tools > Options > Expert Advisors**, tick **Allow algorithmic trading** and **Allow WebRequest for listed URL**, and add: - **https://kintech.asia**
3. Make sure the **Algo Trading** button on the toolbar is green.



Figure 1. Tools > Options > Expert Advisors

1. Allow algorithmic trading
2. Allow WebRequest for listed URL
3. Add the server address
4. Press OK

Figure 2. The Algo Trading button on the toolbar must be on (green)

2. Attach the EA to a chart

1. Open the chart of the **same instrument as the master**, for example XAUUSD. The name may differ at your broker (XAUUSD.m, XAUUSDc...) - use your broker's gold symbol.
2. Drag **Kintech_EA** onto the chart. **Common** tab: tick **Allow Algo Trading**.
3. **Inputs** tab:

INPUT	VALUE
License server	**https://kintech.asia**
Mode	**Copy**
Panel	**true**

4. Press **OK**. The panel opens on the **SETTINGS** tab the first time.

> **IMPORTANT**
> Use only one chart per account for copying. If a second Copy EA is attached for the same account (another chart or terminal), it shows **STANDBY** and does nothing until the first one is removed.



Figure 3. EA window - Common tab

1. Tick Allow Algo Trading
2. Press OK after filling in the Inputs tab



Figure 4. EA window - Inputs tab (Copy mode)

1. License server https://kintech.asia · Mode Copy · Panel true

3. Settings (SETTINGS tab)

FIELD	MEANING
COPY SIGNAL	Click the box to open the list of copy signals (scroll with ▲ ▼, the bar or the mouse wheel): code, price (**FREE** or $/month), symbol and your payment status. Click a row to choose it. The line below shows the signal name, the master balance and your balance. **RELOAD** loads the list again
START COPY FROM LEVEL	1 = copy every order of each master chain. 5 = start copying from the 5th order of the chain (1 - 50)
COPIED LOT	**DEFAULT**: lot from the master lot and the lot mode below. **DECREASE TO MIN LOT**: see below
LOT MODE	**MULTIPLIER**: master lot x value. **BALANCE RATIO**: master lot x (your balance / master balance) x value
LOT VALUE	The value used by the lot mode (above 0, max 100)

Press **SAVE & APPLY**. **CANCEL** discards changes that are not saved.



Figure 5. SETTINGS tab - Copy mode

1. COPY SIGNAL: click the box to choose one signal (price, symbol, payment status); the line below shows your balance
2. START COPY FROM LEVEL
3. COPIED LOT: DEFAULT or DECREASE TO MIN LOT
4. LOT MODE: MULTIPLIER or BALANCE RATIO
5. LOT VALUE
6. SAVE & APPLY



Figure 6. The signal list (opens over the fields below) - scroll with ▲ ▼, the bar or the mouse wheel

- **Paid signal**: the EA asks you to confirm, then shows **WAIT PAYMENT** and copies no new chains. Pay via Telegram **@kintechasia_official** or **@kintechasia_backup** (send your account number and the signal code). As soon as KintechAsia confirms the payment, copying starts by itself and runs until the paid months end. When they end (**EXPIRED**), chains being copied keep following the master until they close; new chains are not copied.

> **TIP**
> Lot and start-level changes apply to **new master chains**. Chains that are already being copied keep the settings they started with.

Lot examples

SETTING	MASTER ORDER	YOUR ORDER
Multiplier, value 0.5	0.04	0.02
Multiplier, value 2	0.03	0.06
Balance ratio, value 1 - your balance 5,000, master 10,000	0.10	0.05
Decrease to min lot, start level 5 - master levels 5 / 6 / 7 are 0.02 / 0.03 / 0.04	0.02 / 0.03 / 0.04	0.01 / 0.02 / 0.02

Lots are rounded to your broker's lot step. A lot below the broker minimum becomes the minimum lot.

Decrease to min lot works like the virtual orders of Direct mode: the start level opens with the broker's minimum lot (for example 0.01), and the next levels grow with the same ratio as the master's lots. The lot mode is not used.

4. How copying works

- **Only new chains.** When you start copying, chains the master already has open are skipped. Copying starts with the next chain the master opens.
- **Same number of orders.** Every new master order (from your start level) is copied, whatever the price difference. If the connection drops, missing orders are opened when it is back.
- **Closing follows the master.** When the master closes or clears a chain, your copied orders of that chain are closed together, at the same moment.
- **Margin.** If there is not enough free margin, the order is retried after 60 seconds and the problem is written in ERROR LOGS.
- **Your other orders are never touched.** The EA only manages its own copied orders.

> **IMPORTANT**
> Do not close a copied order by hand while the master still holds it - the EA opens it again to match the master.

5. Read the COPY tab

- **Header**: source name and status.
- **Info line**: source code, lot settings, start level and magic number.
- **MASTER**: orders open on the master. **COPIED**: your copied orders / master orders you follow. **P/L**: profit of your copied orders. **SERVER**: time since the last server answer.
- **DISABLE COPY / ENABLE COPY** button.



Figure 7. COPY tab

1. Source name and status
2. Info line: source code, lot, start level, magic
3. MASTER, COPIED, P/L, SERVER
4. DISABLE COPY / ENABLE COPY (section 6)

STATUS	MEANING
CONNECTING	Contacting the server
COPYING	Copying normally
STANDBY	Another Copy EA already runs for this account (another chart or terminal). This chart places and closes nothing; it takes over about 2 minutes after the other one stops
NO NEW	Trading was disabled for your account by KintechAsia: no new chains; chains being copied keep following the master, new levels included
PAUSED	The copy source is paused by KintechAsia: no new orders; copied orders still close with the master
MANAGE ONLY	License not valid: no new orders; copied orders still close with the master
WAIT PAYMENT	Paid signal waiting for the payment confirmation: no new chains are copied
EXPIRED	The paid months of the signal ended: no new chains; chains being copied keep following the master until they close
NOT PAID	Payment not confirmed or access revoked - contact KintechAsia
STOPPING	You pressed DISABLE COPY - waiting for the chains being copied to close
SWITCHING	You changed the copy signal - waiting for the copies of the old signal to close
STOPPED	Copying is off
NO SOURCE	Choose a copy signal in SETTINGS
OFFLINE	Server not reachable for a while. Copied orders stay; they sync again when the server is back
ERROR	The server refused the copy signal - choose another one in SETTINGS

6. Stop copying (DISABLE COPY)

1. Press **DISABLE COPY** and confirm.

2. Status **STOPPING**: no new chains are copied. Chains being copied keep following the master - **new levels are still copied** - until the master closes them. This protects you from holding an incomplete chain when the master closes it.
3. When no copied order is left, the status becomes **STOPPED** and the EA stops contacting the copy source.
4. Press **ENABLE COPY** to copy again. Only chains that the master opens after that moment are copied.

> **NOTE**
> ENABLE COPY is locked while the status is STOPPING. It becomes available once every copied order is closed.

7. Change the copy signal

Choose another signal in SETTINGS and press SAVE & APPLY. One signal per account: if copied orders are still open, the EA asks you to confirm.

- No copied order open: the EA switches at once.
- Copied orders open: status **SWITCHING**. The old signal gets no new chains, its chains being copied keep following the master until they close, then the EA switches to the new signal by itself. Choose the old signal again to cancel the switch.

8. How copied orders look

- Comment: **KintechCopy-XAUUSD01|5** = symbol, slot 01, level 5 of the master chain. The KintechCopy prefix marks copied orders.
- Magic number: 9 + your account number + 99 + slot. Do not change it.

Symbol	Time	Type	Volume	Price	Profit	Comment
xauusd	2026.10.28 13:36:16	buy	0.01	4048.95	-1.02	KintechAsia-XAUUSD10|1
xauusd	2026.10.28 15:45:31	buy	0.01	4050.44	-2.51	KintechCopy-XAUUSD10|1
xauusd	2026.10.28 15:45:54	buy	0.01	4048.70	-0.77	KintechCopy-XAUUSD03|1

Figure 8. MT5 Toolbox > Trade: copied orders carry the KintechCopy- prefix (KintechAsia- = Direct mode orders)

9. ERROR LOGS

Short connection drops are listed as info lines in **ERROR LOGS**; problems that last more than about 10 seconds are marked as problems.

MESSAGE	WHAT TO DO
No connection to the server	Add the server address to WebRequest (step 1) and check the internet
Network error 1003 ... retrying	The connection dropped - the EA retries by itself
copy source ... does not exist	The signal was removed - choose another one in SETTINGS
Not enough margin to copy ...	Retried after 60 seconds - add funds or lower the lot
Master has not reported for ... s	The master is offline - your copies follow its last known orders

Need help? Contact us on Telegram.



Figure 9. ERROR LOGS tab

1. CLEAR empties the list